

## 1 NAME

blaze-add - add a blog post or a page to the BlazeBlogger repository

## 2 SYNOPSIS

```
blaze-add [-pqCPV] [-b directory] [-a author] [-d date] [-t title] [-T tags] [-u  
url] [file...]  
blaze-add -h | -v
```

## 3 DESCRIPTION

**blaze-add** adds new blog posts or pages to the BlazeBlogger repository. If supplied, it tries to read data from the existing *files*, otherwise an external editor is opened to let you create a new content.

Note that inside your posts and pages, you can use several special placeholders to be replaced by appropriate data later, when the static content is being generated; the case is not significant, and supported placeholders are as follows:

**%root%**

Relative path to the root directory of the blog; to be used inside links.

**%home%**

Relative path to the website home (index) page; to be used inside links.

**%page[*id*]%**

Relative path to the page with given *id*; to be used inside links.

**%post[*id*]%**

Relative path to the post with given *id*; to be used inside links.

**%tag[*name*]%**

Relative path to the tag with given *name*; to be used inside links.

You can also use a special form, `<!-- break -->`, to mark the end of a part to be displayed on index page.

## 4 OPTIONS

**-b, --blogdir *directory***

Specify the *directory* where the BlazeBlogger repository is placed. The default option is the current working directory.

**-t, --title *title***

Specify the post/page *title*.

- a, -author *author***  
Specify the post/page *author*.
- d, -date *date***  
Specify the post/page date of publishing; the *date* has to be in the YYYY-MM-DD form.
- T, -tags *tags***  
Specify the comma separated list of *tags* attached to the blog post; pages ignore these.
- u, -url *url***  
Specify the post/page *url* to be used instead of the one based on the post/page title. It should consist of alphanumeric characters, hyphens and underscores only, and it is especially useful if non-ASCII characters are present in the title.
- p, -page, -pages**  
Add page instead of blog post.
- P, -post, -posts**  
Add blog post; this is the default option.
- C, -no-processor**  
Disable the use of external processor. Unless the `core.processor` is enabled in the configuration, this is the default behaviour.
- q, -quiet**  
Avoid displaying messages that are not necessary.
- V, -verbose**  
Display all messages. This is the default option.
- h, -help**  
Display usage information and exit.
- v, -version**  
Display version information and exit.

## 5 ENVIRONMENT

### EDITOR

Unless the BlazeBlogger specific option `core.editor` is set, blaze-edit tries to use system wide settings to decide which editor to run. If neither of these options are supplied, the `vi` is used instead as a considerably reasonable choice.

## 6 FILES

*.blaze/config*

BlazeBlogger configuration file.

## 7 SEE ALSO

`blaze-config(1)`, `perl(1)`.

## 8 BUGS

To report bug or even send patch, either add new issue to the project bug-tracker at <http://code.google.com/p/blazeblogger/issues/>, or visit the discussion group at <http://groups.google.com/group/blazeblogger/>. You can also contact the author directly via e-mail.

## 9 AUTHOR

Written by Jaromir Hradilek <jhradilek@gmail.com>.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts.

A copy of the license is included as a file called FDL in the main directory of the BlazeBlogger source package.

## 10 COPYRIGHT

Copyright (C) 2008, 2009 Jaromir Hradilek

This program is free software; see the source for copying conditions. It is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE.